

Evie Carry All Trio

Skill level: Intermediate

Designed by
Sara Lanan



Make this cute ensemble with a sunglass case, make-up bag and purse.

Fabric Needed (For all three items)

Exterior Fabric	1 3/4 yds
Lining Fabric	1 3/4 yds

Materials Needed (For all three items)

Pellon [®] 810 Tru Grid [™]	1 3/4 yds
Pellon [®] 809 Décor Bond [®]	3/4 yd
Pellon [®] 72F Peltex [®] II	1/4 yd
Pellon [®] SF101 Shape-Flex [®]	1/4 yd
Pellon [®] 987F Fusible Fleece	1/8 yd
22" Zipper	
9" Zipper	
1/2" Round Velcro	
Thread	
Fabric Marker	

Tools Needed


Sewing Machine and related supplies
Rotary cutting rulers and supplies

Purse Instructions - All seam allowances are 1/4" unless otherwise noted.

Cut out all pieces following instructions on the Tru Grid® Layout Page.

Mark all fold and pin locations with a pencil or fabric marker.

Cut all Pellon® products 1/4" less on all sides than the pattern pieces unless otherwise noted.




Straps - make two

Fold one strap in half lengthwise, right sides out and press. Open strap and place right side down.

Align Décor Bond edge, fusible side down with the strap centerline. Fuse according to manufacturer's instructions.

Fold all edges under 1/4" and press. Fold strap in half lengthwise, wrong sides together. Topstitch 1/8" from edge on the three open sides. Topstitching along the folded edge is optional.




Exterior and Lining

For Exterior Only

Fold the two accent pieces in half lengthwise, right sides out. Press. Set aside.




Fold the main panel pleats. The bottom line should be on top of the top line. Press. Insert the accent pieces between the pleats with the folded edge up, in between the fold of the pleat. Pin in place.




Topstitch 1/8" from the top folded edge of the pleat.


Repeat for second pleat location.




Exterior panel should look like the diagram.



Flip the exterior main panel over, wrong side up. Place the Pellon® Peltex® II and Décor Bond® on the wrong side of the exterior main panel. Fuse according to manufacturer's instructions.




Match the straps to pin locations on the right side of the main panel. Pin and sew a rectangle 1 1/4" x 2". Set the exterior main panel aside.




For Lining Only

Fold under pocket pieces 1/4" on all sides and press. Sew 1/8" along top side. Place pockets on pattern marking locations right side up on the right side of the lining main panel. Topstitch sides and bottom 1/8" from the folded edges. Leave the top unstitched.



Fuse Décor Bond® to the wrong side of the two exterior top pieces. With right sides together, baste one long edge of the two exterior top pieces using a 1/4" seam allowance. Press seam open. Align right side of zipper with wrong side of exterior top pieces along the basted seam. Pin and sew.



Repeat for lining top pieces without Décor Bond and zipper.


Place exterior side pieces and exterior top pieces right sides together. Sew together. Press seams. Topstitch along the top of each side piece 1/8" from the seam. Cut off excess zipper length.





Repeat for lining except for zipper instructions.



Remove the basting stitch. Open the zipper. Center the bottom of the side panels right sides together on the main panel marks that indicate the area that makes the bottom of the purse. Pin and sew in place. Line up the top and side panel with the main panel right sides together. Snip the curved edge of the main panel to ease into place onto the top panel. Pin in place and sew. Turn right side out and press the seams.




Repeat for lining pieces.



With lining wrong side out, place the lining into the exterior with wrong sides together. Line up the bottom, sides and top.

Hand stitch the lining to the zipper.



Make Up Bag

Finished Size 6 3/4" x 3 1/2" x 1 1/2"


Place the fusible side of the Shape-Flex® on the wrong side of the exterior fabric pieces. Fuse according to manufacturer's instructions.

With right sides together, baste one long edge of the two exterior top pieces. Press seam open. Align right side of zipper with wrong side of exterior top pieces along the basted seam. Pin and sew.


Repeat for lining top pieces without stabilizer and zipper.

Remove basting and open the zipper. Match the raw edges of the two exterior top pieces with the exterior main panel, right sides together. Snip on the exterior top pieces to match the curve of the exterior main panel. Pin and sew in place. Cut off excess zipper length. Turn right side out and set aside.

Repeat for lining (no zipper).




Zipper Placement



Place the lining into the exterior, wrong sides together. Line up the bottom, sides and top.

Hand stitch the lining to the zipper.



Sunglasses Case Finished Size 6 1/2" x 3 3/4"

Place the fusible side of the Fusible Fleece on the wrong side of the exterior main panel and flap. Fuse according to manufacturer's instructions.

Place the hook Velcro piece on the right side of the lining flap. Sew in place.


Place the other Velcro piece on the right side of the exterior main panel. Sew in place.



Match the exterior flap and exterior main panel on the end opposite the velcro dot, right sides together. Pin and sew.

Repeat with the lining main panel and lining flap.

Fold open both the exterior and lining and press the seams flat.




Match and lay the lining and exterior pieces right sides together. Pin and sew, leaving the bottom open.


Leave open →




Turn right side out and press the seams. Topstitch 1/8" from the bottom finished edge.



Fold the main panel in half with lining on the inside. Make sure Velcro locations match.




Topstitch 1/8" around the sides and flap.



Tru Grid™ Layout for Evie Carry All Trio

Draw pattern pieces on Tru Grid following dimensions below. Print Arch Template Page to draw arches for the pattern pieces. Note all placement markings on pattern pieces. Transfer all markings to fabric, following pattern pieces.



Arch Templates for Purse, Make-up Bag and Sunglasses Case

Print out templates. Lay templates under the Tru-Grid™ to mark your arches on your pattern pieces.

